



Installationshinweise MPI-200 Programmieradapter



Systemvoraussetzungen:

- Betriebssystem: WinXP (ab SP3), Vista (ab SP1), Win7
- Prozessor: min. 1 GHz CPU
- Freier Festplattenspeicher: min. 10 MB (mit .NET bereits installiert)
- Windows Installer: 3.1
- NET-Version: 4.0 (bitte vorher installieren)
(<https://www.microsoft.com/en-us/download/details.aspx?id=17851>)
- USB: 1 freie USB Schnittstelle USB 2.0
- Zugriffsrechte: Administrator für die Installation

Installation der Software:

- Durch einen Doppelklick auf die Datei „MPI Installer_SW V2.0.2.1.msi“ wird der Installationsvorgang gestartet
- Folgen Sie den Anweisungen des Installations-Assistenten
- Nach erfolgreicher Installation erscheint folgendes Symbol auf dem



Installing hints MPI-200 Programming adapter



System requirements:

- Operating system: WinXP (SP3 and higher), Vista (SP1 and higher), Win7
- Processor: min. 1 GHz CPU
- Available hard disk space: min. 10 MB (.NET is already installed)
- Windows installer: 3.1
- 4.NET version 4.0 (install before)
(<https://www.microsoft.com/en-us/download/details.aspx?id=17851>)
- USB: 1 vacant USB interface USB 2.0
- Access rights: Administrator rights for installation

Installing the software:

- Double-click on the "MPI Installer_SW V2.0.2.1.msi" file to start the installation
- Follow the instructions of the installation wizard
- After the installation is finished, the following symbol appears on the desktop:

